



# SkyFile Mail – Automatic Dialling

1. Go to **Configuration > Account+Dial parameters...** from the menu options. Enter your **Master username** and **Master password** as required and click OK




A dialog box titled "SkyFile" with a close button (X) in the top right corner. It contains two text input fields: "Master username:" and "Master password:". To the right of the "Master username:" field is an "OK" button, and to the right of the "Master password:" field is a "Cancel" button.

2. Go to the lower portion of "Account and dial parameters" and select the option **Automatic dialling**




A "Dial parameters" dialog box. It has several input fields: "Do not send files bigger than" (2048 KByte), "Min. time between dial retries" (5 min), and "Dial retries" (1). There are two radio buttons: "Manual dialing (standard)" and "Automatic dialling:". The "Automatic dialling:" option is selected, indicated by a red arrow. Below the radio buttons is a "Fixed times:" text box and a "Periodic:" section with "Start:", "End:", and "Period:" (min) input fields.

3. **Automatic dialling at Fixed times:** Select this option if you require automatic dial-in at fixed times during a 24 hour period. Enter the exact time (in increments of 15 minutes – i.e. 00/15/30/45), separating times with a space



A "Dial parameters" dialog box. It has several input fields: "Do not send files bigger than" (2048 KByte), "Min. time between dial retries" (5 min), and "Dial retries" (1). There are two radio buttons: "Manual dialing (standard)" and "Automatic dialling:". The "Automatic dialling:" option is selected. Below the radio buttons is a "Fixed times:" text box containing the value "9:00 12:30 15:00 19:45". There is also a "Periodic:" section with "Start:", "End:", and "Period:" (min) input fields.

4. **Automatic dialling Periodic:** Select this option if you require automatic dial-in within a fixed time-slot, with periodic intervals. Enter the start time frame, End time frame and the periodic (minute). For example, choose a Start Time of 07:00, an End Time of 19:00 and a Period of 45 min



A "Dial parameters" dialog box. It has several input fields: "Do not send files bigger than" (2048 KByte), "Min. time between dial retries" (5 min), and "Dial retries" (1). There are two radio buttons: "Manual dialing (standard)" and "Automatic dialling:". The "Automatic dialling:" option is selected. Below the radio buttons is a "Fixed times:" text box which is empty. There is also a "Periodic:" section with "Start:" (07:00), "End:" (19:00), and "Period:" (45 min) input fields.